Setting Up Your POP or IMAP Email Address in Microsoft Outlook

This tutorial shows you how to set up Microsoft Outlook 2003® to work with your e-mail account. This tutorial focuses on setting up Microsoft Outlook 2003, but these settings are similar in other versions of Microsoft Outlook. You can set up previous versions of Microsoft Outlook by using the settings in this tutorial.

To Set Up Your E-mail Account in Microsoft Outlook

1. In Microsoft Outlook, from the E-mail Accounts menu, select Tools.



2. On the E-mail Accounts wizard window, select **Add a new e-mail account**, and then click **Next**.



3. For your server type, select POP3 or IMAP, and then click Next.



4. On the Internet E-mail Settings (POP3/IMAP) window, enter your information as follows:

   Your Name
   Your first and last name.

   E-mail Address
   Your email address.

   User Name
   Your email address, again.

   Password
   Your email account password.

   Incoming mail server (POP3)

POP, Pop.secureserver.net or IMAP, imap.secureserver.net.

Outgoing mail server (SMTP)
Smtpout.secureserver.net

Click More Settings.

NOTE: "smtpout.secureserver.net" is an SMTP relay server. In order to use this server to send e-mails, you must first activate SMTP relay on your e-mail account. Log on to your Manage Email Accounts page to set up SMTP relay. If you do not have SMTP relay set up and your Internet Service Provider (ISP) allows it, you can use the outgoing mail server for your Internet Service Provider. Contact your Internet Service Provider to get this setting.



5. On the **Internet E-mail Settings** window, go to the **Outgoing Server** tab.
6. Select **My outgoing server (SMTP) requires authentication**.
7. If you did not change the SMTP relay section, select **Use same settings as my incoming mail server**. If you changed the user name and password in the SMTP relay section of your Manage Email Accounts page, select **Log on using** and enter the user name and password. The following example assumes you did not change your SMTP relay section in your Manage Email Accounts page.



8. Go to the **Advanced** tab, and then change the Outgoing server (SMTP) port to **80** or **3535**.
9. Click **OK**.



10. Click **Next**.



11. Click **Finish**.



NOTE: As a courtesy, we provide information about how to use certain third-party products, but we do not endorse or directly support third-party products and we are not responsible for the functions or reliability of such products. Outlook 2003® is a registered trademark of Microsoft Corporation in the United States and/or other countries. All rights reserved.